



```
*****  
*                               P1025TWR Board                               *  
*                               Version 1.1.2                               *  
*****
```

This file contains release information about the P1025TWR board.

Release Information:

=====
This image can be used for P1025TWR board.

I. Hardware board support and software version:

~~~~~  
P1025TWR

- U-boot: 2011.09 (Jan 05, 2012)
- Linux version 2.6.35.14 (gcc version 4.3.2 (GCC))
- Atheros driver version: 9.2.0\_U10.1020
- Firmware version: v1.1.2

II. Hardware board and corresponding files:

~~~~~  
P1025TWR:

- tftpdn-p1025twr-nor.vbs
- twr-p1025_32b.dtb
- uImage
- root.squashfs

III. Features in this Release:

~~~~~  
1. Wireless WiFi functionality:

- Supports 2 mPCIe Atheros XB-114 WiFi cards (chipset AR9390, version V2.2)
- 802.11a/b/g/n to 500M(Dual band)
- Only WiFi AP mode support.

## 2. Network Attached Storage functionality:

- Disk filesystem supports XFS/FAT32/EXT2/EXT3/EXT4/NTFS.
- Disk management supports Volume management and RAID management.
- Account Management supports LDAP, User account/group management.
- Sharing management supports SAMBA, FTP, NFS, HTTP.
- Backup service supports Snapshots, Rsync Server, Rsync Client.
- Backup strategy supports Instant/ Schedule/Auto-sync backup, back up to external storage device or from external storage.

## 3. Network Video

- RTSP/RTCP/RTP/HTTP.
- Capturing/Forwarding/Record/Playback/Search/VOD
- MP4V/H.264/MJPEG
- CIF/VGA/D1/HD1080p
- Play/pause/stop/faster/slower/search
- Matrix display/Full Screen display
- Live-viewing by Hand-Held devices which support WIFI, e.g. iPhone, iPad, HTC HD2 and so on
- Ability to run on multiple cores and in Giga-bit switch network.
- Maximum output streaming bit-rate is up to 180Mbps.
- Auto detection of devices logon and logoff

## 4. Network router functionality:

- Static IP/router
- DHCP Server/Client
- DNS,DDNS
- UPNP
- NAT/PAT
- IGMP
- PPPoE
- VLAN
- VPN(pass through, PPTP client/server, IPsec)
- RIPv1/v2
- 3G uplink



#### 5. Network security functionality:

- Firewall
- IDS
- IPS

#### 6. System configuration & management

- HTTP/HTTPS based Web GUI management
- SSH/Telnet management
- Firmware update
- Configuration data backup & restore
- Support Linux SMP mode

#### 7. Media Service

- UPNP
- DLNA
- BitTorrent

#### 8. Smart Energy

- Support for ZigBee HA 1.0 Home Automation providing remote monitoring and control of appliances via supported Smart Plugs

#### IV. How to update the image:

---

1. Open tftp server and secureCRT with a baud rate of 115200
2. Run script file tftpdn-p1025twr-nor.vbs in secureCRT to update P1025TWR image.
3. uImage, root.squashfs can be used for both P1025TWR board.
4. twr-p1025\_32b.dtb is used for P1025TWR.
5. u-boot.bin is used for P1025TWR board.

#### V. Known Issues and Workaround:

---

1. Squashfs filesystem compiled with Ubuntu Linux cannot run on this board.

#### V. Documentation:



~~~~~

The documents available with this release are:

1. P1 Tower System Module LTIB Quick Start Guide.

web link is <http://compass.freescale.net/livelink/livelink/open/219285001>

VI. How to Contact Us:

~~~~~

You can contact us via email, newsgroups, voice, fax or the Freescale website. For details on contacting Freescale, visit <http://www.freescale.com> or write to us at: [Support@freescale.com](mailto:Support@freescale.com)

=====

May 27, 2011 Freescale Corporation

Freescale, the Freescale logo, are registered trademarks of Freescale Inc. All other trademarks are hereby recognized as the property of their respective owners.